

Package ‘cropDemand’

January 26, 2021

Type Package

Title Spatial Crop Water Demand for Brazil

Version 1.0.1

Description Estimation of crop water demand can be processed via this package. As example, the data from 'TerraClimate' dataset (<http://www.climatologylab.org/terraclimate.html>) calibrated with automatic weather stations of National Meteorological Institute of Brazil is available in a coarse spatial resolution to do the crop water demand. However, the user have also the option to download the variables directly from 'TerraClimate' repository with the `download.terraclimate` function and access the original 'TerraClimate' products. If the user believes that is necessary calibrate the variables, there is another function to do it. Lastly, the estimation of the crop water demand present in this package can be run for all the Brazilian territory with 'TerraClimate' dataset.

License CC BY 4.0

Encoding UTF-8

LazyData true

Depends R (>= 3.2.0),

Imports dplyr(>= 0.3.0.1), ggplot2(>= 3.3.2), raster, rgdal, tidy,
ncdf4

BugReports <https://github.com/FilgueirasR/cropDemand/issues>

RoxygenNote 7.1.1

NeedsCompilation no

Author Roberto Filgueiras [aut, cre] (<<https://orcid.org/0000-0002-0186-8907>>),
Luan P. Venancio [aut] (<<https://orcid.org/0000-0002-5544-8588>>),
Catariny C. Aleman [aut] (<<https://orcid.org/0000-0002-3894-3077>>),
Fernando F. da Cunha [aut] (<<https://orcid.org/0000-0002-1671-1021>>)

Maintainer Roberto Filgueiras <betofilgueiras@gmail.com>

Repository CRAN

Date/Publication 2021-01-26 17:30:02 UTC

R topics documented:

download_terraclimate	2
eto_calibration	3
loadROI	4
monthly_stack	5
plot_AWC	6
ppt_calibration	6
see_brazil_biomes	7
see_brazil_states	7
waterDemand	8

Index	10
--------------	-----------

download_terraclimate *Download of reference evapotranspiration (eto) and rainfall (ppt) from 'TerraClimate'*

Description

This function will download the eto and ppt and will load a rasterstack according to the the region of interest (Region and sub_region).

Usage

```
download_terraclimate(dir_out, variable, years, region, sub_region)
```

Arguments

dir_out	Directory where you want to save the raster images that you are goind to download.
variable	Variable to download. This function will download the eto or ppt (Rasterstack).
years	The period in years that the function should download images.
region	Use the "brazil" shapefile to extract the Rasterstack (variable) for one state (Brazilian state), or use the "biomes_brazil" to extract the Rasterstack (variable) for one biome of Brazil.
sub_region	You have two options in this section, if you choice the brazil (in region parameter) you need to choice the Brazilian states, but if you choice the biomes_brazil (in region parameter) you must choice one of Brazilian biomes.

Value

Download for the region of interest the ppt (Rainfall) or eto (reference evapotranspiration) rasterstack

References

The images used in this package can be found in the paper: Abatzoglou, J.T., S.Z. Dobrowski, S.A. Parks, K.C. Hegewisch, 2018, Terraclimate, a high-resolution global dataset of monthly climate and climatic water balance from 1958-2015, Scientific Data.

Examples

```
## Not run:

### Downloading eto based on Brazil states.
see_brazil_states()

img<-download_terraclimate(variable = "eto",
                           years = c(2018:2019),
                           region = "brazil",
                           sub_region = 13)

### Downloading the ppt based on Brazil biomes.
see_brazil_biomes()

img<-download_terraclimate(variable = "ppt",
                           years = c(2018:2019),
                           region = "biomes_brazil",
                           sub_region = 6)

## End(Not run)
```

eto_calibration

Calibration of reference evapotranspiration (eto) of 'TerraClimate'

Description

This function will calibrate the reference evapotranspiration (eto) from TerraClimate dataset based in the relationship with observed weather stations data.

Usage

```
eto_calibration(slope, intercept, eto_stack)
```

Arguments

slope	the slope of the linear regression (numeric).
intercept	the intercept of the linear regression (numeric).
eto_stack	stack of eto.

Value

Returns a Rasterstack of eto calibrated.


```

image_rainfall<-loadROI(variable = "ppt",
                        region = "brazil", sub_region = 13)

#For Brazilian Biomes:

see_brazil_biomes()

image_tmin<- loadROI(variable = "eto", region = "biomes_brazil",
                     sub_region = 2)# sub regions: 1:6 (biomes)

## End(Not run)

```

monthly_stack	<i>Function to calculate the mean monthly rainfall/reference evapotranspiration to generate the crop water demand</i>
---------------	-----------------------------------------------------------------------------------------------------------------------

Description

This function will calculate the mean monthly air temperature based on the period of time selected (start_date and end_date).

Usage

```
monthly_stack(stack, start_date, end_date)
```

Arguments

stack	Stack of mean rainfall/reference evapotranspiration Rasterstack
start_date	Date that start the investigation, should be in the following format (2000-01-01 /Year-Month-Day)
end_date	Date that end the investigation, should be in the following format (2017-12-31 /Year-Month-Day)

Value

Returns a stack with a monthly mean air temperature from a period of time

Examples

```

## Not run:
start_date <- c('2000-01-01')
end_date <- c('2017-12-01')
monthly_rainfall <- monthly_stack(stack = rainfall_stack,
                                 start_date = start_date, end_date = end_date)

## End(Not run)

```

plot_AWC	<i>Function to plot the percentage of Available Water Capacity (AWC)</i>
----------	--------------------------------------------------------------------------

Description

This function will plot the monthly AWC

Usage

```
plot_AWC(AWC_stack)
```

Arguments

AWC_stack A stack generated in WaterDemand function

Value

Returns a plot (gg file) of monthly percentage of AWC

Examples

```
## Not run:  
plot_AWC(AWC_stack)  
  
## End(Not run)
```

ppt_calibration	<i>Calibration of rainfall (ppt) of 'TerraClimate'</i>
-----------------	--------------------------------------------------------

Description

This function will calibrate the rainfall (ppt) from TerraClimate dataset based in the relationship with observed weather stations data.

Usage

```
ppt_calibration(slope, intercept, ppt_stack)
```

Arguments

slope the slope of the linear regression (numeric).
intercept the intercept of the linear regression (numeric).
ppt_stack stack of ppt.

Value

Returns a Rasterstack of ppt calibrated.

Examples

```
## Not run:  
  
ppt_cal<- ppt_calibration(slope = 0.7000972,  
                          intercept = 23.753785, ppt_stack = ppt);  
  
## End(Not run)
```

see_brazil_biomes	<i>Function to see the Brazilian biomes available tp use in download.terraclimate and loadROI function</i>
-------------------	------------------------------------------------------------------------------------------------------------

Description

This fuction will show the biomes available in the package and how we can call each biome polygon.

Usage

```
see_brazil_biomes()
```

Value

The biomes information available to run the cropDemand package.

Examples

```
## Not run:  
see_brazil_biomes()  
  
## End(Not run)
```

see_brazil_states	<i>Function to see the Brazilian states available to use in download.terraclimate and loadROI function</i>
-------------------	------------------------------------------------------------------------------------------------------------

Description

This function will show the Brazilian state available in the package and how we can call each state polygon.

Usage

```
see_brazil_states()
```

Value

The Brazilian state information available in the package to run the cropDemand package.

Examples

```
## Not run:
see_brazil_states()

## End(Not run)
```

waterDemand	<i>Function to generate the water demand based in available water capacity of the soil</i>
-------------	--------------------------------------------------------------------------------------------

Description

This function will calculate the water balance parameters based in the available water capacity informed (AWC). The output water balance parameters for this function are:

1. ARM - storage;
2. ALT - alteration;
3. ETR - actual evapotranspiration;
4. DEF - deficit;
5. EXC - excess;
6. REP - replacement;
7. RET - withdrawal;
8. AWC_arm - percentage of storage compared to AWC;

Usage

```
waterDemand(out_dir, ppt_stack, eto_stack, AWC)
```

Arguments

out_dir	output directory where you want to save the variables
ppt_stack	Stack of mean rainfall Rasterstack calculated in monthly_stack function
eto_stack	Stack of mean evapotranspiration Rasterstack calculated in monthly_stack function
AWC	The available water capacity (AWC) that the function will use in the calculations. The AWC value must be chosen according to the crop (root system depth) you want to obtain the water balance.

Value

Returns multiple Rasterstack object as output (explained in description).

Examples

```
## Not run:  
cwd<- waterDemand(out_dir = "G:/My computer/test/CropWaterDemand",  
                  ppt_stack = rainfall_image, eto_stack = eto_image, AWC = 100)  
  
## End(Not run)
```

Index

[download_terraclimate](#), 2

[eto_calibration](#), 3

[loadROI](#), 4

[monthly_stack](#), 5

[plot_AWC](#), 6

[ppt_calibration](#), 6

[see_brazil_biomes](#), 7

[see_brazil_states](#), 7

[waterDemand](#), 8